



Project System SAP Implementation at IESCO

Training Document

Prepare Proposal Estimates

PD Construction





Contents

P	repare P	roposal	3
1	Purpo	ose	3
		Process Steps (PD Construction)	
		Copy Standard Network (Engineering)	
		Copy Standard Network (Material)	
		Assign Reference Point to Network Activity and Costing Sheet	
	1.1.4	Create Network (Services)	27
	1.1.5	Transfer WBS BOM	38





Prepare Proposal

1 Purpose

Document

Detailed Project Cost Estimate preparation for admin approval is covered in this document, this estimate project will be used to create operative project by coping it.

Prerequisites

Standard Network Templates should be created in the system, if they don't exist than new networks can be created from scratch.





1.1 Process Steps (PD Construction)


1.1.1 Copy Standard Network (Engineering)

Use

After Copying WBS Structure from template, Networks are added to estimation project for detail planning

Procedure

1. Access "Project Builder" App from Fiori Launchpad:







- 2. Click OPEN button to open the project.
- 3. Click Search Help button and you can find either through description or through project code, i.e. PE* or PL* is entered in the Project definition field.




4. Press Enter








5. Select required Project and press enter



- 6. Expand project structure where to add Network (This expension is just for example, it depend on user where he require to add)
- 7. Right Click on ie "PE.2018-85-0001-1" and select create and choose network.












8. Add Description of the Network Header and enter MRP Controller which is used to control the authorizations at lowest level.




Field name	Description	User action and values	Comments
Network Description		Example:	Enter short description for network header.
		ThattiKelra - Engineering and Design	
MRP Controller		Example:	Number of the responsible
		321	





9. Right Click on the Network and selcet Include and Choose Standard Network.




- 10. Open Search Help
- 11. Either Press enter or search through Network / Description.

Field name	Description	User action and values	Comments
Standard Network		Example:	Standard Network Header
		10*	Number





12. Standard Network List will appear.




13. Choose Standard network as per scenario / situation requirement ie 10000011






14. Activity List will appear, Press Enter







15. Add / Remove and adjust scenarios as per project requirement.



16. Press Save.

Result:

Network Copied from Template (Standard Network)






1.1.2 Copy Standard Network (Material)

Use

After Copying WBS Structure from template, Networks are added to estimation project for detail planning

Procedure

1. Access "Project Builder" App from Fiori Launchpad:



2. Click OPEN button to open the project.





3. Click Search Help button and you can find either through description or through project code, i.e. PE* or PL* is entered in the Project definition field.




4. Press Enter








5. Select required Project and press enter




- 6. Expand project structure where to add Network (This expension is just for example, it depend on user where he require to add)
- 7. Right Click on ie "PE.2018-85-0001-2" and select create and choose network.







8. Add Description of the Network Header and enter MRP Controller which is used to control the authorizations at lowest level.




Field name	Description	User action and values	Comments	
Network Description		Example:	Enter short description for	
		ThattiKelra - Material	network header.	
MRP Controller		Example:	Number of the responsible	
		321		

Project System Training Document PAGE 16 OF 42





9. Right Click on the Network and selcet Include and Choose Standard Network.




- 10. Open Search Help
- 11. Either Press enter or search through Network / Description.

Field name	Description	User action and values	Comments
Standard Network		Example:	Standard Network Header
		10*	Number





12. Standard Network List will appear.




13. Choose Standard network as per scenario / situation requirement ie 10000012






14. Activity List will appear, Press Enter







15. Add / Remove and adjust scenarios as per project requirement.



16. Press Save.

Result:

Network Copied from Template (Standard Network)






1.1.3 Assign Reference Point to Network Activity and Costing Sheet

Use

Reference Points are the logical link between WBS BOM and Network Activities for transferring material components at the time of estimation preparation.

Procedure

1. Access "Project Builder" App from Fiori Launchpad:




2. Click OPEN button to open the project.



1 Entry found




3. Click Search Help button and you can find either through description or through project code, i.e. PE* or PL* is entered in the Project definition field.








5. Select required Project and press enter







- 6. Expand project structure where to add Network (This expension is just for example, it depend on user where he require to add)
- 7. Select Material Activity (Internal Activity) and maintain Reference Points for BOM Transfer Link and Costing Sheet for 8% Installation Charges & 12% Material Handling Charges








		Pro	ject Builde	r: Proje	ct PE.20	18-85-0001			
Back Project planning board Hierarchy graphic			phic	Network graphic Mass change Intermediate Save					
dentification	and view	selectio	n						
Activity Detail: Overview(s):			0000262 ()	0020	HT Mat	erial			9
Internal	Extnl	Dates	Assignmen	nts L	ong Text	User fields	Qualification	Additional data	Progress
General assi		The second		D611970		TI sessesses			
WBS elemen Company Co		1000	18-85-000	1-2		Network		410000000262	
Business Are	а		200		Object currency Costing Sheet	ency	PKR		
Plant		200				neet	ZPS002		
Profit Center		10101				Overhead key	кеу		
Change Num	ber					Tax Jur.			
Functional Area			Object Class		Investment				
Reference point RC		R0000	002			☐ Subnet	wk exists		
Ref. Elem.							12		







8. Press Save

Result:

Network Copied from Template (Standard Network)

Project System Training Document PAGE 26 OF 42






1.1.4 Create Network (Services)

Use

Following steps are used to Add / Create Services Network in the estimate project.

Procedure

1. Access "Project Builder" App, Form Fiori Launchpad.



2. Click OPEN button to open the project.






3. Click Search Help button and you can find either through description or through project code, i.e. PE* or PL* is entered in the Project definition field.




4. Press Enter







5. Select required Project and press enter




6. Expand project structure where to add Network (This expension is just for example, it depend on user where he require to add)






7. Right Click on PE.2018-85-0001-3 and select create and choose network.








8. Enter Description, MRP Controller as per user/project requirement.








9. Click on Network Header and either double click on Service Activity or use facility provided by SAP, Drag and Drop Services Activity over Network Header to make it part of Network.







10. Add Description of the Service Activity. And maintain relevant data required








Field name	Description	User action and values	Comments
Network Activity Description		Example: Carriage and Erection of Pole	Enter short description for network header.
Material Group		Example: SG01	Differentiate the type of Work. For Services there is only one Material Group
Purchasing Organization		Example: 4000	Identify which Organization is requesting for procurement
Purchasing Group		Example: 028	Department requesting for procurement.

11. Press Enter, Service Specification Screen will appear



Field name	Description User action and values		Comments
Short Text		Example:	Description of Service
		Carriage and Erection of 36' Pole	
Quantity	Requirement quantity	Example:	

Project System Training Document PAGE 34 OF 42






		3
Un	Unit of Measure	Example:
		EA
Gross Price	Price per Unit	Example:
		2500
Cost Element	Account Head where cost of service will be posted and will appear in	Example:
	Trial	750620
Short Text		Example: Description of Service
		Carriage and Erection of 45' Pole
Quantity	Requirement quantity	Example:
		7
Un	Unit of Measure	Example:
		EA
Gross Price	Price per Unit	Example:
		4600
Cost Element	Account Head where cost of service will be posted and will appear in	Example:
	Trial	750620





12. Press Back







13. Press Save

Result:

Services Network & Activity created in the system.

Note:

• Outline Agreement will be required at the time of PR generation in Operative project (PC).






1.1.5 Transfer WBS BOM

Use

Following steps are followed during Transfer of WBS BOM to Estimate Project.

Procedure

1. Access the activity using one of the following navigation options:







2. Update the following required and optional fields


Field name	Description	User action and values	Comments
Project Definition		Example:	Enter the project definition for which you want to
		PE.2018-85-0001	transfer the WBS BOM.
WBS Element		Example:	Enter the WBSE relevant to the selection of
		PE.2018-85-0001-2	activities to transfer the WBS BOM.
Profile		Example:	Profile determines default values for BOM
		Z001	Transfer
Material		Example:	Header material for which you want to create
		99908	the WBS BOM
Plant	A place where materials are produced, or goods and	Example:	
	services are provided	200	
BOM Usage	This key defines the area (such as engineering/design	Example:	
_	or production) where a BOM can be used	F	

Project System Training Document PAGE 39 OF 42






3. Press Enter



4. Click Execute button








5. Click button No



6. Click Enter







- 7. Click Save Button
- 8. If any material that has no price maintained system will display warning message, click yes button to continue.

Result:

WBS BOM has been transferrd on the respective project network activities.

Note:

• Reference Points are the Prerequisite.

Project System Training Document PAGE 42 OF 42