



# Project System SAP Implementation at IESCO Training Document Change WBS BOM CE PMU – PD GSC





## **Contents**

Change WBS BOM	3
1 Purpose	
1.1 Process Steps (PMU / GSC)	
1.1.1 Copy WBS BOM	
1.1.2 Create Change Number	
1.1.3 Change WBS BOM	
1.1.4 BOM Comparison	1





# **Change WBS BOM**

# 1 Purpose

## **Document**

Change in WBS BOM requires if the project cost estimate is revised and at the time of handing taking process. Any addition / deletion and/or change in quantity of material will be directly handled in operative projects instead of WBS BOM. (Main purpose is for material comparison only)

## **Prerequisites**

Original WBS BOM should exist before changing it.





# 1.1 Process Steps (PMU / GSC)


# 1.1.1 Copy WBS BOM

## Use

Following steps are followed during copying WBS BOM from one WBS to another WBS.

## **Procedure**

1. Open "Create WBS BOM" App, from Fiori Launchpad.







2. Enter Following detail on the screen and press "Copy WBS BOM"

MPC	вом	17
MPS	DOM	***

Field name	Description	User action and values	Comments
WBS Element		<b>Example:</b> PG.1713.1718.1.001.2	Enter the WBS element key, to which the WBS BOM is assigned.
Material		Example: 99900	Enter the material number, to which the WBS BOM is assigned.
Plant		Example: 202	Enter the Plant number relevant to the WBS BOM
BOM Usage		Example:	Enter the usage relevant to the WBS BOM

	Copy WBS BOM	>
WBS Element	PI.1708-1718.1.001.2	
Material	99900	
Plant	202	
BOM Usage	F WBS BOM	
Effectivity		
Change Number		
Valid From	20.04.2018	
Renumber		






3. Enter Following detail on the screen and press "Copy WBS BOM"

Field name	Description	User action and values	Comments
WBS Element		<b>Example:</b> PI.1708.1718.1.001.2	Enter the WBS element key, to which the WBS BOM is assigned.
Material		<b>Example:</b> 99900	Enter the material number, to which the WBS BOM is assigned.
Plant		Example: 202	Enter the Plant number relevant to the WBS BOM
BOM Usage		Example:	Enter the usage relevant to the WBS BOM


4. Press Enter and select the material items to copy, and press Copy button.







## 5. Data will be copied from one WBS BOM to another WBS BOM







6. Press Save Button.

## Result:

WBS BOM has been copied.






# 1.1.2 Create Change Number

## Use

Following steps are followed during creation of ECR Number for recording WBS BOM changings.

## **Procedure**

1. Open "Create Change Master" App, From Fiori Launchpad.








## 2. Update the following required and optional fields:

Field name	Description	User action and values	Comments
Profile		Example:	Profile identification that contains default values and pre settings for the
		Z0000001	creation of a change master record

#### 3. Press Enter








## 4. Update the following required and optional fields

Field name	Description	User action and values	Comments
Change Number Description		Example:	Text that describes the change number.
		For WBS – PG.1713-1718.1.001.2	
		Reconcile Material for HO/TO and A90 process (This case will not be transferred to project)	
Valid From		Example:	Enter the start of the validity period of the change
		21.04.2018	number. Changes will not be effective before this date
Reason For Change		Example:	General information about the reason for change.
		Material Returned / Material Revised	
Status of change number		Example:	Active / Not active for Changes
		01 - Active	

# 5. Click Objects button Objects







### 6. Update the following required and optional fields:

Field name	Description	User action and values	Comments
WBS Element		Example:	Enter the WBS element key, to which the WBS BOM is assigned.
		PG.1713-1718.1.001.2	
Material		Example:	Enter the material number, to which the WBS BOM is assigned.
		99900	
Plant		Example:	Enter the Plant number relevant to the WBS BOM
		202	
BOM Usage		Example:	Enter the usage relevant to the WBS BOM
		F	
Description		Example:	Description of the change that is made to a WBS BOM
-		For Material Comparison	

## 7. Click SAVE button

## **Result:**

Engineering Change number has been generated, and it will be used to change WBS BOM s that change record can be available for comparison purpose.






# 1.1.3 Change WBS BOM

## Use

Following steps are followed during Changing WBS BOM, it will only be used for comparison purpose.

## **Procedure**

1. Open "Change WBS BOM" App, from Fiori Launchpad.








## 2. Update the following required and optional fields:

Field name	Description	User action and values	Comments	
WBS Element		Example:	WBSE for which you want to create WBS BOM	
		PG.1713-1718.1.001.2		
Material		Example:	Header material for which you want to create the WBS BOM	
		99900		
Plant		Example:	A place where materials are produced, or goods and services are provided	
		202		
BOM Usage		Example:	This key defines the area (such as engineering/design or production)	
		F	where a BOM can be used	
Change Number		Example:	Number used to uniquely identify a change master record.	
		50000000019		


### 3. Change WBS BOM Screen will appear







4. Adjust the quantity of material whose estimate is revised



5. Update the following required and optional fields:

Field name	Description	User action and values	Comments
Component for item 0010		<b>Example:</b> 10112	Material number of the components that you enter, as part of the WBS BOM.
Quantity for item 0010		Example:	Quantity of the BOM component
		1 from 2	

6. Press Enter or click Save Button

## Result:

WBS BOM has been changed.

## Note:

• Transfer this changed WBS BOM to the operative project (Refer to the training manual Detailed Planning Procurement – Transfer WBS BOM)

Project System Training Document PAGE 15 OF 19






# 1.1.4 BOM Comparison

#### Use

Following steps are followed during the WBS BOM Comparison (if required).

### **Procedure**


- 1. Open "BOM Comparison" App, Form Fiori Launchpad.
- 2. Select go to choose Primary BOM Category and press Project option








3. Select go to choose Secondary BOM Category and press Project option







4. Fields will be adjusted according to WBS BOM for comparison data.



5. Update the following required and optional fields:

Field name	Description	User action and values	Comments
WBSE Element(primary BOM)		<b>Example:</b> PG.1713-1718.1.001.2	Enter the WBSE relevant to the primary BOM.
Material (primary BOM)		Example: 99900	Enter the BOM header material number relevant to the primary BOM.
Plant		Example: 202	A place where materials are produced, or goods and services are provided
BOM Usage		Example:	This key defines the area (such as engineering/design or production) where a BOM can be used
Valid From(Primary BOM)		<b>Example:</b> 21.04.2018	Enter the validity date relevant to the primary BOM.

Project System Training Document PAGE 18 OF 19





Change Number (secondary BOM)	<b>Example:</b> 500000000014	Enter the change number relevant to the secondary BOM.
WBS Element (secondary BOM)	<b>Example:</b> PT.1505-1617.1.001.2	Enter the WBSE relevant to the secondary BOM.
Material (secondary BOM)	<b>Example:</b> 99900	Enter the BOM header material number relevant to the secondary BOM.
Plant	Example: 202	A place where materials are produced, or goods and services are provided
BOM Usage	Example:	This key defines the area (such as engineering/design or production) where a BOM can be used

6. Press Comparison button

SAP BOM Comparison: Result (Differentiated) Menu V Set Filter Change I Back Exit Cancel System V Sort in Ascending Order Sort in Descending Order Spreadsheet.. Local File. Send... Primary BOM-WBS BOM Secondary BOM-WBS BOM **WBS** Element **WBS** Element PG.1713-1718.1.001.2 PG.1713-1718. Material 99900 Material 99900 Usage: Usage: Plant: 202 Plant: 202 Date: 21.04.2018 Date: 20.04.2018 Change Number 500000000019 O... Component number Object description Comp. Qty (CUn) 1 Unit Comp. Qty (CUn) 2 Unit Lv 0 şab. 10112 Transformer 1 EA 2 EA 1 10123 5 M 5 M Meter Wire

# **Result:**

WBS BOM Comparion report is opened.

Project System Training Document PAGE 19 OF 19