



Project System SAP Implementation at IESCO Training Document Project Structuing CE PMU – PD GSC





Contents

Project Sti	ructuring	3
	pse	
	Process Steps (PMU / GSC)	4
	Create Project from Standard/Template Project	4
1.1.2		





Project Structuring

1 Purpose

Document

Copying the standard structure into estimate project for proposal preparation is covered in this document

Prerequisites

Standard Templates should be created in the system to adopt a standardized structure of all estimates, if they don't exist than new project can be created from scratch provided the standard structure (IESCO's PMU/GSC or PDC finalized structure) is known.





1.1 Process Steps (PMU / GSC)


1.1.1 Create Project from Standard/Template Project

Use

Following steps are followed during Creating Estimation Project by using Template (Standard Structure).

Procedure


1. Access "Project Builder" App, From Fiori Launchpad.








2. Press Menu - Project - New - Copy Project



3. Click Copy project menu item







4. Update the following required and optional fields:

Field name Description		User action and values	Comments	
Project def.		Example: PI.1707	The project definition contains dates and organizational information that are binding for the entire project.	






Description	Example: Project Name 8th STG (Year 2017-2018) Estimate	
Start	Example: 18.04.2018	Planned start date for the project
Project Profile	Example: Y000001 CE/PMU	The profiles contain default values and control parameters for processing WBS, Network, Activities and functions in the project
Std project def.	Example: SP.1507	The standard project definition contains dates and organizational information that are binding for the entire project. A project structure that will be used as a template for creating new projects

5. Click Open Number button

6. Press Find Next Number








4. Update the following required and optional fields:

Field name	Description	User action and values	Comments
Start value		Example: Pl.1707	Start value for the search area, in which the next free standard project number is to be determined.






5. Press Copy button or press Enter:



6. Click WBS element overview button








7. Press Replace Button

8. Update the following required and optional fields:

Field name	Description	User action and values	Comments
Search		Example:	Search WBS Codes to be replaced
		SP.1507	
Replace		Example:	WBS code to be replaced by existing code
		PI.1708	








- 9. Press Replace Button (again if codes still varies)
- 10. Update the following required and optional fields:

Field name	Description	User action and values	Comments	
Search		Example:	Search WBS Codes to be	
		PI.1708-1516	replaced	
Replace		Example:	WBS code to be replaced	
		PI.1708-1718	by existing code	

Note:

• WBS Codes varies from situation to situation, it depends on the user how he is working or managing the project.




11. Press Check button to identify if any error exist





12. Press Include button



13. Press Save after adjusting the structure as per requirement.

Result:

Estimation Project WBS Structure has been created from Template.






1.1.2 Include WBS In to Project from Standard/Template

Use


Following steps are followed during addition within the structure.

Procedure

1. Access "Project Builder" App, From Fiori Launchpad:




2. Click OPEN button to open the project.



Project System Training Document PAGE 13 OF 20








4. Press Enter after entering search criteria




5. Select required Project and **press enter**








- 6. Expand project structure up to PI.1708-1718.1where to add further WBS Element Structure (This expension is just for example, it depend on user where he require to add)
- 7. Right Click on WBS PI.1708-1718.1 select Include and choose WBS Element








8. Select Standard WBS, and in "Below" Field add the WBS which needs to be included along with its hierarchy and then press WBS Element Overview Button.








9. Adjust the Description of WBS Elements and press Replace Button.







10. Update Fields as below




Field name	Description	User action and values	Comments
Search		Example:	Search WBS Codes to be
		SP.1507-1516.1.001	replaced
Replace		Example:	WBS code to be replaced
		PI.1708-1718.1.002	by existing code






11. Press Check and Include







12. Press Save to finally include the newly added hierarchy in the original planned structure after making adjustment as per user/project requirement.



Result:

New WBS Structure is added within the Project.

Note:

- $\bullet \quad \mbox{ In Case of PMU / GSC}$, One Project contail full year Projects.
- In Case of PD Construction, Every Proposal is a Project.